

MOVEit Central 9.0 Installation Guide



Copyright

©1991-2016 Ipswitch, Inc. All rights reserved.

This document, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the express prior written consent of Ipswitch, Inc.

The content of this document is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Ipswitch, Inc. While every effort has been made to assure the accuracy of the information contained herein, Ipswitch, Inc. assumes no responsibility for errors or omissions. Ipswitch, Inc., also assumes no liability for damages resulting from the use of the information contained in this document.

WS_FTP, the WS_FTP logos, Ipswitch, and the Ipswitch logo, MOVEit and the MOVEit logo, MessageWay and the MessageWay logo are trademarks of Ipswitch, Inc. Other products and their brands or company names, are or may be trademarks or registered trademarks, and are the property of their respective companies.

This document was published on Tuesday, February 09, 2016 at 11:25.

Contents

Overview	3
The MOVEit Central Installation Program.....	4
Requirements.....	5
Database Considerations	6
Update Notes	7
Install MOVEit Central	9
Welcome	10
License Agreement.....	11
License.....	12
Setup Options.....	13
Credentials	14
Database Type	16
Folders	19
Tamper Detection Key	20
Certificate Dialog	21

Email Options	22
Finish	23
Update MOVEit Central	26
<hr/>	
Welcome	26
License.....	27
Ready to Update	29
Update Complete	30
Repair MOVEit Central	31
<hr/>	
Modify MOVEit Central	33
<hr/>	
Uninstall MOVEit Central	36
<hr/>	
Install MOVEit Central Web Admin	38
<hr/>	
Supported Features in Web Admin.....	39
Install or Update Web Admin.....	40
Repair or Remove Web Admin.....	47
Connect to MOVEit Central with Web Admin.....	52
Index	55
<hr/>	

Overview

To install MOVEit Central, run the setup program. Install MOVEit Central on a server-class machine. Other applications and/or services can be run on the same machine. For more information, see ***Requirements*** (on page 5).

To configure MOVEit Central:

- Install MOVEit Central Admin on the same machine as the MOVEit Central server, or on an administrator's machine.
- You can configure MOVEit Central remotely using MOVEit Central Web Admin. For more information, see ***Install MOVEit Central Web Admin*** (on page 38).

Note: Some features are available only in the Central Admin Console. For more information, see ***Supported Features in Web Admin*** (on page 39).

During installation, you can choose either MySQL or Microsoft SQL Server as a database engine.

The MOVEit Central Installation Program

The MOVEit Central installation program installs, upgrades, repairs, or uninstalls MOVEit Central software.

IMPORTANT: With version 8.1 and subsequent versions, MOVEit Central and MOVEit Central Admin use separate installation programs.

- **New installations:** Install MOVEit Central, and then install MOVEit Central Admin (the Admin Console, also known as VBAAdmin) either on the server where you installed MOVEit Central or on a remote system.
- **Existing installations:** If MOVEit Central and MOVEit Central Admin are already installed, an update installation to MOVEit Central uninstalls the existing MOVEit Central Admin from the Central server. You must install MOVEit Central Admin separately.

NOTE: Version 9.0 includes MOVEit Central Web Admin. For more information, see *Installing MOVEit Central Web Admin* (on page 38). You can run the MOVEit Central Web Admin and the Admin Console concurrently.

The following installation options are available.

Installation Option	Does this:
Install (on page 9)	<ul style="list-style-type: none"> ▪ Detects that MOVEit Central software is not on the system. ▪ Installs MOVEit Central software.
Update (on page 26)	<ul style="list-style-type: none"> ▪ Detects that an older version of MOVEit Central software is present. ▪ Installs new versions of MOVEit Central components and applications. ▪ Implements database changes/conversions.
Repair (on page 31)	<ul style="list-style-type: none"> ▪ Reinstalls all components that were originally installed with the identical version of MOVEit Central.
Modify (on page 33)	<ul style="list-style-type: none"> ▪ This option is available only if the installation program detects that the most recent version of MOVEit Central is present. ▪ Adds or removes various MOVEit Central components and applications. ▪ Might perform database changes/conversions.
Uninstall/Remove (on page 36)	<ul style="list-style-type: none"> ▪ This option is available if the installation program detects that the most recent version of MOVEit Central is present. ▪ Uninstall/Remove is also available from the Windows Control Panel > Add/Remove Programs.

Before you perform an update or repair option, back up your critical files. For more information, see *MOVEit Central User's Guide* in the section **Central Service - Backup - Disaster Recovery** (<http://docs.ipswitch.com/moveit/central81/help/admin/en/index.htm#27426.htm>).

Requirements

- **Hardware:**

- A server with a 2 GHz processor
- 1 GB RAM
- 80 GB SATA or SAS hard drive
- 100/1000 MB Ethernet interface (for TCP/IP traffic).

A faster processor, faster hard drives and more memory are recommended for busy sites.

NOTE: MOVEit Central does not need to be the only application or service running on this machine.

- **Operating system (one of the following):**

- Windows Server 2008 R2 (64-bit English and German)
- Windows Server 2012 R2
- Windows Server 2012
- Support for virtual servers running on VMware ESX (64-bit) and Microsoft Hyper-V 1.0 (64-bit)

NOTE: We recommend that you *do not* run MOVEit Central Admin (VBAdmin) on Windows Server 2012 R2, because of instability related to the VB run-time. MOVEit Central server is fully supported on Windows Server 2012 R2, but MOVEit Central Admin should be run on a separate system.

- **Database (one of the following):**

- MySQL (5.5.47) (included in the MOVEit Central installation)
- Microsoft SQL Server 2008 R2 Enterprise/Standard (Not Data Center)
- Microsoft SQL Server 2012 Enterprise/Standard
- Microsoft SQL Server 2014 Enterprise/Standard

- **.NET Framework versions required:** MOVEit Central requires .NET 4.5 for the AS2 and PGP modules. The MOVEit Central installer detects whether .NET 4.5 is present, and can install .NET using the .NET web install. This requires the server to have internet access. If the server does not have internet access, you must install .NET by other means before you run the MOVEit Central installation program.

- **Remote administration of MOVEit Central with MOVEit Central Admin (VBAdmin):**

- Use the MOVEit Central Admin (VBAdmin) installation program to set up the client on each of your remote desktops. In addition to the operating systems shown above, you can also install MOVEit Central Admin on Windows 7 Professional/Enterprise, and Windows 8.
- **Server certificate:** If you plan to use MOVEit Central Admin remotely, a server certificate is recommended though not required. The MOVEit Central installation package automatically installs a self-signed certificate for this purpose. If you want to use your own SSL certificate instead, you must install it (usually through the Microsoft "Certificates" Management Console), select it with the MOVEit Central Configuration utility, and restart the MOVEit Central service.

- **Web Admin requirements:**
 - Server requirements for Web Admin are the same as the requirements for MOVEit Central server. See above. Web Admin can be installed on the same server as the MOVEit Central server, or on a separate server that can communicate with the MOVEit Central server.
 - **Supported browsers for Web Admin:** Chrome (Windows only); Mozilla Firefox (Windows, Mac, and Red Hat Linux); Internet Explorer 11 (Windows only); Safari (Mac only)

Optional: Supported Antivirus Engine

When Symantec AntiVirus, McAfee VirusScan, or Trend Micro OfficeScan detect a virus, MOVEit Central takes action to delete or ignore the infected files and log the appropriate message. Installing one of these antivirus packages is recommended if you want MOVEit Central to use its free, integrated antivirus feature.

Database Considerations

MySQL Database

If you want to use MySQL as your database engine, it is strongly recommended that you *do not* install MOVEit Central software on a computer that already has a copy of MySQL running.

On computers where MySQL does not exist, the MOVEit Central installation program installs its own copy of MySQL.

However, if MySQL already resides on the computer, it is difficult for the MOVEit Central installation program to detect MySQL installations that use non-standard service names or port numbers. Additionally, an arbitrary pre-installed copy of MySQL might be a version that is not compatible with MOVEit Central.

Microsoft SQL Server Database

If you choose SQL Server as your database engine, you must install your own copy of the database engine prior to installing MOVEit Central.

For information about installing MOVEit Central in failover mode, see Failover (Enterprise Only) in the "Central Service" chapter of the *MOVEit Central User's Guide*.

Update Notes

You can use the same setup program to upgrade MOVEit Central as you would use to install a new copy of the software. Update any remotely-installed MOVEit Central Admin clients soon after updating MOVEit Central.

Note: If you are currently running Version 7.x or earlier, you must first upgrade to Version 8.0.

Before you update, make sure that no tasks are about to run just before you apply the upgrade. There are two ways to accomplish this:

- Use the MOVEit Central Admin **Disable Scheduler** command to turn off the scheduler so no new tasks can be started. (Check the **Status** tab for remaining running tasks.) The update shuts down the MOVEit Central service before installing the new software. This lets you look at the MOVEit Central system (for example, look at Reports of the last completed tasks) before performing the upgrade.
- Use the MOVEit Central Admin **Shut Down Service** command to automatically shut down the service after all currently running tasks have completed. Doing so means that the update does not need to shut down the MOVEit Central service before applying the new software. This eliminates the chance that new tasks (or the scheduler) could be started by another operator.

When moving MOVEit Central from one server to another: If you copy MOVEit Central configuration files or database files from a different server that was running an older version of MOVEit Central than is installed on the new server, you might need to rerun the installer to convert the files to a newer format. To do this, run the installer again and choose the **Repair** option. If the installer is for a newer version of Central than is already installed, this step is not needed, because the update procedure automatically converts the files.

Windows Firewall: If the Windows Firewall is running, the setup program creates an exception for MOVEit Central, so it can listen for TCP connections. This is required to support connections from MOVEit Central Admin, as well as for active mode FTP data transfers. If Failover is enabled in your license, the setup program also enables file and print sharing to permit manual synchronization in a failover configuration. If you are using a software firewall other than Windows Firewall, you might need to manually create an exception for the programs MICentral.exe and MIAS2.exe.

64-bit version: MOVEit Central 9.0 is installed as a 64-bit version. Support for 64-bit Windows provides increased performance for task processing.

MOVEit Central 9.0 also introduces a 64-bit Central API.

The MOVEit DMZ API does not have 64-bit support. If you have custom scripts that use the 32-bit MOVEit Central API or the MOVEit DMZ API, you can run the installation program again and use the **Modify** option to switch to the 32-bit version of MOVEit Central. For more information, see ***Modify MOVEit Central*** (on page 33).

Licenses

The update to MOVEit Version 9.0 products requires that you have a license file. License keys from previous versions will no longer work.

- **License Files:** To get a new license file, follow the steps in this *KB article* (<http://ipswitchft.force.com/kb/articles/FAQ/How-do-I-obtain-a-license-file-for-an-upgrade-to-MOVEit-Central-8-1-or-higher>). If you need further assistance, **contact Ipswitch MOVEit Support** (<http://www.ipswitchft.com/support>).

NOTE: Before you update, back up your existing license file. If you need to roll back the installation, you will be required to re-apply your old license file. To locate your existing license file, follow the steps in this *Knowledge Base article* (<http://ipswitchft.force.com/kb/articles/FAQ/How-do-I-locate-my-current-MOVEit-Central-license-file-or-serial-number>).

Updating from MOVEit Central versions

If you are updating from:	Do this:
MOVEit Central 8.0 or later	Upgrade directly to MOVEit Central 9.0
MOVEit Central 7.x or earlier	First, update to version 8.0, and then update to version 9.0

Licensees

Licensees who are licensed for one or more of the MOVEit products can upgrade, at no additional cost, under their prepaid maintenance coverage. Copies of the version 9.0 products will be placed on the *Ipswitch MOVEit Customer Portal* (<https://ipswitchft.secure.force.com/cp/>) and email notifications will be sent to the designated technical contacts at select licensees. For all customers, we recommend that you:

- Download a new license file
- Download the MOVEit Central 9.0 application

If you need further assistance with license issues, contact *Ipswitch MOVEit Support* (<http://www.ipswitchft.com/support>).

Onsite Evaluators

Evaluators who are doing an onsite evaluation of one or more of the above MOVEit products can upgrade to version 9.0, at no additional cost, after it is commercially released. Copies of version 9.0 will be placed on the *Ipswitch Customer Portal* (<https://ipswitchft.secure.force.com/cp/>), and email notifications sent, so that onsite evaluators can log in, download, and install the software. If a new evaluation license is needed in order to evaluate version 9.0, onsite evaluators can request a license from their Ipswitch sales representative.

Install MOVEit Central

Use this procedure if you are installing MOVEit Central for the first time.

If you have already installed an earlier version of MOVEit Central, follow the instructions at *Update MOVEit Central* (on page 26).

Prerequisites:


- Meet the *System Requirements* (on page 5),
- Obtain a License file.

MOVEit Central requires a license file to install and operate. To obtain a license file, contact **Ipswitch MOVEit Support** (<http://www.ipswitchft.com/support>).

- Back up your critical files (repair, modify options). For more information, see *MOVEit Central User's Guide* in the section *Central Service - Backup - Disaster Recovery* (<http://docs.ipswitch.com/moveit/central81/help/admin/en/index.htm#27426.htm>).

Welcome

- 1 Run the setup program. The Welcome screen appears.



- 2 If you have previously partially completed this installation, the screen includes the option to Use parameters from MOVEit_Central.INI. Check this option to auto-fill all fields using your previous entries.


An Installation Config File was found from a previous MOVEit Central Installation attempt. Check the box below to use these installation parameters.

☒ **Use parameters from C:\MOVEit_Central.INI**

- 3 Click Next.

License Agreement


- 1 Read the license agreement.



- 2 Select I accept the terms of the license agreement.
- 3 Click Next.

License


- 1 MOVEit Central requires a license file to install and operate. License keys from previous versions will no longer work. To get a new license file, follow the steps in this **KB article** (<http://ipswitchft.force.com/kb/articles/FAQ/How-do-I-obtain-a-license-file-for-an-upgrade-to-MOVEit-Central-8-1-or-higher>). If you need further assistance, **contact Ipswitch MOVEit Support** (<http://www.ipswitchft.com/support>).



- 2 Click Browse and select the license file.
- 3 Click Next.

Setup Options

- 1 Depending on your needs and familiarity with the product, you can perform an express or custom installation.



- 2 Select one of the following options:
 - **Express Setup** - Select this option if you are setting up an evaluation server or want to install MOVEit Central quickly. Express setup uses the following values:
 - Application folder: C:\Program Files\MOVEit
 - Database engine: MySQL
 - Service: Run as user "micsvc"
 - Credentials: Auto-generated
 - Certificate: Create new test certificate

If you selected **Express Setup**, click **Next** and then go to **Email Options** (on page 22).

- **Custom Setup** - Select this option to customize all options.

- **Disable selection of existing users (faster)** - This option affects the Credentials screen. Normally, the installation prefills drop-down boxes with the names of all users on your local system and domain, in case you want to use an existing user for credentials purposes. However, on some systems, querying the domain controller can be very time-consuming. If this computer is a member of a domain with many users or if the connection to the domain controller is slow, choose this option so that the installer does not present you with a list of all users.

If you selected **Custom Setup**, click **Next** and then go to **Credentials** (on page 14).

Credentials

MOVEit Central uses several sets of credentials to control access to its configuration and administration.

- 1 Select a user to administer MOVEit Central remotely and a user to run the MOVEit Central service:
 - **Administer MOVEit Central Remotely As:**
 - **New User** - Creates a new remote user. A suggested user name and password appear. You can change these if required. Optionally click **Suggest** to generate a new password, or enter a specific password in the third box.
 - **Existing User** - Lets you select an existing user. Enter that user's password. This option is not available if you disabled selection of existing users in **Setup Options** (on page 13).
 - **"MOVEit Central" Service Will Run As:**


- **New Admin** - Creates a new user for Central to run under. A suggested Admin name and password appear. You can change these if required. Optionally click **Suggest** to have the program generate a new password, or enter a specific password in the third box.
- **Existing Admin** - Lets you select an existing user for Central to run under. Enter that user's password in the box provided. This option is not available if you disabled the selection of existing users in *Setup Options* (on page 13).

Note: If MOVEit Central cannot locate the correct credentials, you are prompted to provide them.

2 Click Next.

Database Type

MOVEit Central can use either a MySQL or a Microsoft SQL Server database.



- 1 Choose the database engine for MOVEit Central to use:
 - **MySQL** - a small-footprint database engine that MOVEit Central will install and administer. See MySQL below.
 - **Microsoft SQL Server** - If you select this option, you must have an already-installed instance of SQL Server, and provide the following information:
 - **Server name** - The hostname or IP address of the server. If the server using a non-standard port, add a command and the port number after the hostname.
 - **Instance (if needed)** - This is typically blank.
- 2 Click Next, and then go to the appropriate database below for further instructions.

My SQL

If you selected MySQL as your database engine, following dialog box appears.

The screenshot shows the 'InstallShield Wizard' window titled 'MySQL Database Credentials'. The subtitle reads: 'MOVEit Central maintains administrative and user-level MySQL database credentials'. On the left is a vertical banner for 'MOVEit CENTRAL' with the text 'Highly Secure, Easy-to-use, IT-approved Managed File Transfer Solution'. The main area contains instructions: 'The following credentials (user : password) are required to set up MOVEit Central. You may generate suggested passwords to the the grey boxes with "Suggest", or type your own into the white boxes.' Below this, under 'Database Credentials:', there are two rows. The first row is 'Database Administrator: root : [grey box] [white box with dots]'. The second row is 'Database User: micentral : [grey box] [white box with dots]'. A 'Suggest' button is positioned above the password boxes. At the bottom are buttons for 'Help', '< Back', 'Next >', and 'Cancel'.

- 1 Provide the following information:
 - **Database Administrator** - The superuser account for MOVEit Central. The database administrator is always **root**. Click **Suggest** to have the install suggest a password, or enter a password in the box provided.
 - **Database User** - The standard account for MOVEit Central. Enter the database username. Click **Suggest** to have the install suggest a password, or enter a password in the box provided.
- 2 Click **Next**, and then go to **Folders** (on page 19).

Microsoft SQL Server

If you selected Microsoft SQL Server as your database engine, the following dialog box appears:

The screenshot shows the 'MOVEit Central - InstallShield Wizard' window. On the left is a logo for 'MOVEit CENTRAL' with the text 'Highly Secure, Easy-to-use, IT-approved Managed File Transfer Solution'. The main area is titled 'Microsoft SQL Server Credentials' and contains the following sections:

- Supply credentials for the existing Microsoft SQL Server.**
 - Credentials to be used during the install:**
 - ☐ Use Windows Authentication during install
for user DOC-MARKT\WIN\admin
 - ☒ Use SQL Server authentication during install
 - Existing SQL Administrator:** sa
 - and password:**
 - Database to create:** micstats
- Credentials to be used by MOVEit Central:**
 - ☐ Use Windows Authentication
 - ☒ Use SQL Server authentication
 - New SQL username:** micentral
 - and password:**

At the bottom are buttons for 'Help', '< Back', 'Next >', and 'Cancel'.

1 Enter the following information:


- **Credentials to be used during the install** - Provide the credentials to access the existing instance of Microsoft SQL Server. Select an authentication type to use during installation:
 - **Use Windows Authentication during install** - The currently logged-on user will be used. There must be a corresponding user with the same password on the Windows server running SQL Server, and this user must be authorized in SQL Server.
 - **Use SQL Server Authentication during install** - Specify an existing SQL Server username and password.
- **Database to create** - You must specify the name of the database to create. In most cases you can accept the default.
- **Credentials to be used by MOVEit Central** - Select an authentication type to be used by MOVEit Central:

- Use Windows Authentication - The user under which the service runs will be used. A corresponding user with the same password must exist on the Windows server that is running SQL Server, and this user must be authorized in SQL Server.
- Use SQL Server Authentication - Specify an SQL Server username and password to create.

2 Click Next, and then go to **Folders** (on page 19).

Folders

MOVEit Central installs its application files and set up its database in folders you specify here.




1 Enter the following:

- **Application Folder** - Enter the folder path, or click **Browse** to locate the folder. *Recommended:* Locate the MOVEit Central application where you normally install applications. Some configuration and log files are also kept here, but the total size is typically less than 100 MB.
- **Cache Folder** - Enter the folder path, or click **Browse** to locate the folder. The Cache folder requires more space; therefore install it on your largest available local or SAN drive.
- **Database Folder (MySQL installations only).** Use the default location C : \MySQL or Browse to select a different location for the database.

2 Click Next.

Tamper Detection Key

MOVEit Central uses the following key to protect audit information in the database, so you can detect whether unauthorized changes have been made to the audit tables.




- 1 **Tamper Key** - Enter an arbitrary string or click **Suggest** to have the installation program suggest a random key.

Important: If you are installing a failover pair, you must use the same tamper detection key on both machines.

- 2 Click **Next**.

Certificate Dialog

An SSL certificate allows MOVEit Central to encrypt its communications with remote copies of MOVEit Central Admin.



- 1 Select one of the following options to either create a self-signed (test) certificate, or select an existing SSL certificate:

- **Create New Certificate** - The installation will generate, install, and assign an untrusted self-signed certificate good for 3,000 days.
- **Use Existing Certificate** - Select an existing SSL certificate from the list.

Note: If you purchased failover and want to install it, MOVEit Central must first be successfully installed on each node.

For more information on Ipswitch Failover, see *Ipswitch Failover 9.0 Online*

Content <http://ipswitchft.force.com/kb/articles/FAQ/Ipswitch-Failover-9-0-Online-Content>.

- 2 Click Next.

Email Options


Email notifications about serious errors will be sent to the email addresses you enter here.

The screenshot shows the 'Email Options' window of the 'MOVEit Central - InstallShield Wizard'. The window has a title bar with the text 'MOVEit Central - InstallShield Wizard' and a close button. Below the title bar, the text 'Email Options' is displayed, followed by the instruction 'Please enter the addresses used to send email about serious errors.' On the left side, there is a logo for 'MOVEit CENTRAL' with the tagline 'Highly Secure, Easy-to-use, IT-approved Managed File Transfer Solution'. The main area contains three input fields: 'Email server:' with the value 'smtp.abc.com' and an example 'Example: smtp.xyz.com'; '"To" email address:' with the value 'support@abc.com' and an example 'Example: support@xyz.com'; and '"From" email address:' with the value 'micentral@abc.com' and an example 'Example: notify@xyz.com'. At the bottom, there are four buttons: 'Help', '< Back', 'Next >', and 'Cancel'.

- 1 Enter the following:
 - Email Server - The SMTP server of the email address.
 - "To" email address - The email address where the notification will be sent.
 - "From" email address - The email address from which notifications will be sent.
- 2 Click Next.


Finish

MOVEit Central is ready to install.



- 1 Click Next to install MOVEit Central.
- 2 After installation completes, you can perform additional tasks:
 - View installation configuration, including **PASSWORDS** - This is strongly recommended. This is your **ONLY** chance to verify any generated passwords and write them down.
 - View the installation log file - You can review the steps taken during the installation.

- Securely delete the installation files (with overwrite) - This is strongly recommended. DO NOT leave unencrypted passwords on the system.




- 3 Make your selections and click **Next**.
- 4 If you have not already installed MOVEit Central Admin, install it now.

This completes the MOVEit Central installation.

Note: If you run MOVEit Central Admin from any remote desktops, also run the MOVEit Central Admin upgrade on those desktops.

Failed Installation

If an installation fails, the Installation Failed!!! dialog box appears:



- 1 Select one or more of the following:
 - **Securely upload Installation files to Ipswitch** - Uploads install files and log information to Ipswitch for further debugging.
 - **View Installation log**
 - **View Installation configuration** - Displays all the installation configuration options, including passwords.
 - **Delete installation log and configuration files** - This is strongly recommended. It is **IMPORTANT** that you do not leave unencrypted passwords on the system.
- 2 Click **Finish**. Your partial installation is removed. However, your installation settings have been saved. If you re-run this installation, fields will be pre-filled with your last values.


Update MOVEit Central

Use this procedure to update the MOVEit Central software to a newer version.

Note: In some situations, the installation process can appear to be stuck for many minutes on 'Updating runtime libraries.' This appears to be caused by background Windows processes that run after Windows updates are downloaded and installed, but before the machine has been rebooted to finish Windows update installation. If you encounter this issue, your options are: be patient, end the installation through Task Manager and reboot, or (carefully) lower the priorities of the Windows update tasks through Task Manager.

Welcome


- 1 Run the installer. The Update Welcome screen opens.




- 2 Click Next, then go to *License* (on page 27).

License

- 1 MOVEit Central requires a license file to install and operate. License keys from previous versions will no longer work. To get a new license file, follow the steps in this **KB article** (<http://ipswitchft.force.com/kb/articles/FAQ/How-do-I-obtain-a-license-file-for-an-upgrade-to-MOVEit-Central-8-1-or-higher>). If you need further assistance, **contact Ipswitch MOVEit Support** (<http://www.ipswitchft.com/support>).




- 2 Click **Browse** and select the license file. If your license file already exists, as it would for an update, the following screen opens, showing the current license:



- 3 Click **Next**, then go to *Ready to Update* (on page 29).

Ready to Update


The Ready to Update screen opens.



- 1 Click Next, then go to *Update Complete* (on page 30).

Update Complete

The Update Complete screen opens.




- 1 Select the **Securely delete the installation files (with overwrite)** checkbox- This is strongly recommended. *DO NOT LEAVE UNENCRYPTED PASSWORDS ON THE SYSTEM.*
- 2 Click **Finish**.
- 3 If you have not already installed MOVEit Central Admin, do so now. If you run MOVEit Central Admin from any remote desktops, you must also the MOVEit Central Admin update on those desktops.


This completes the MOVEit Central installation.

Repair MOVEit Central

This option reinstalls all components that were originally installed with the identical version of MOVEit Central.




- 1 Select Repair and click Next.




- 2 Click Finish.

Modify MOVEit Central

This option installs/removes MOVEit Central components.



- 1 Select Modify and click Next. The Selected Features screen appears. Select the features to install and clear the selection for the features to uninstall.



- **Common Features:** Features that are common to both the 64-bit and 32-bit versions. In most cases, select this option.


The features that are not part of the Common Features are those that are different depending on whether the 64-bit or 32-bit version is installed. Non-common features include: the MOVEit Central server, the configuration program, the DLLs that they use, and the ODBC driver.

- **MySQL:** In most cases, select this option.

Note: You can run only one of the following versions of MOVEit Central. The default installer installs the 64-bit version. To switch to the 32-bit version, select that check box and clear the check box for the 64-bit version.

- **32-bit MOVEit Central:** Select this option to switch to the 32-bit version of MOVEit Central.
- **64-bit MOVEit Central:** MOVEit Central is installed as a 64-bit version. Support for 64-bit Windows provides increased performance for task processing.


2 Click Next.




3 Click Finish.

Uninstall MOVEit Central

This option completely removes MOVEit Central from the system.




- 1 Select Remove, then click Next.



- 2 Click Yes to confirm the removal.

- 3 If MOVEit Central uses the MySQL database, you are prompted to specify whether to remove the MySQL database that was installed with MOVEit Central. Click **Yes** to remove MySQL or **No** to keep it.



- 4 Click **Finish**.

Install MOVEit Central Web Admin

Prerequisite: ***Install MOVEit Central*** (on page 9).

You can install MOVEit Central Web Admin on the same server or a different server as MOVEit Central. If you install it on a different server, it must be able to connect to the MOVEit Central server.

The Web Admin installer installs an Apache Tomcat web server and a Java web application to support the JavaScript-based Web Admin. The Java web application connects to MOVEit Central using the same TCP ports as MOVEit Central Central Admin Console (VBAdmin).

This program installs or updates the software. It also provides maintenance options to repair the software.

NOTE: The MOVEit Central server supports concurrent connections from MOVEit Central Web Admin and the Admin Console.

Supported Features in Web Admin

MOVEit Central Web Admin is a web browser interface to MOVEit Central. It has a subset of the functions that are available in the Central Admin Console (VBAdmin). Subsequent releases will include additional functionality until the Web Admin becomes a complete replacement for Central Admin.

Functions Implemented in MOVEit Central 9.0 Web Admin

- Hosts
- Tasks
- Task Groups
- Sync Tasks
- Advanced Tasks
- Scripts
- Commands
- Settings
- Task filtering
- Task Status
- Non-Admin User Permissions
- Context-sensitive Help

Features and Functions Not Implemented in MOVEit Central 9.0 Web Admin.

Use the Admin Console for these features and functions:


- Task Run History and Reporting
- Debug Log
- Partial Task Import
- Permissions Configuration

You can install MOVEit Central Web Admin on the same server or a different server as MOVEit Central. If you install it on a different server, it must be able to connect to the MOVEit Central server.


The Web Admin installer installs an Apache Tomcat web server and a Java web application to support the JavaScript-based Web Admin. The Java web application connects to MOVEit Central using the same TCP ports as MOVEit Central Central Admin Console (VBAdmin).

Install or Update Web Admin

- 1 Run the installer. The Update Welcome screen appears.




- 2 Click Next. The License Agreement screen appears.




- 3 Accept the license agreement and click Next. The Destination Folder screen appears.

Note: You can also print the license agreement.



- 4 Accept the default location or click **Change** and browse to a different location, Click **Next**.. The Configure Tomcat screen appears.




- 5** To accept the defaults listed to connect to the Tomcat server for MOVEit Central Web Admin, click **Next**.

– or –

To change the defaults, proceed as follows and click **Next**.

- a) To point to some other location than the default listed, check the box *Specify the IP address or hostname for MOVEit Central*, and type the appropriate information. Specify multiple MOVEit servers with a comma-separated list.
- b) To change the default HTTP port from 80, type the new port number in the *HTTP Connector Port* box.
- c) To change the default HTTPS port from 443, type the new port number in the *HTTPS Connector Port* box.


The Change Service Log On Account? screen appears.



- 6** To accept the defaults to log on with the local system account, click **Next**.

– or –

To choose a different account, select **Yes**, and click **Next**. The Log On Information screen appears.




The screenshot shows a Windows-style dialog box titled "MOVEit Central Web Admin - InstallShield Wizard". The main heading is "Log On Information" with a sub-instruction "Specify a user name and password". The MOVEit Central Web Admin logo is in the top right. Below the heading, a paragraph states: "Specify the user name, password and group membership of the user account that will log on to run this application. It can be a local account or domain account (DOMAIN\Username)." There are three input fields: "User name:" containing "MYDOMAIN\service_acct", "Password:" containing ten dots, and "Group:" containing "Administrators". At the bottom left is the "InstallShield" logo. At the bottom right are three buttons: "< Back", "Next >", and "Cancel".


Type the following information and click **Next**:

- a) **User name:** The user name to log on to the account. For a domain user, precede the user name with the domain name, for example, *mydomain\myuser*.
- b) **Password:** The password for the user.
- c) **Group:** The group to which the user belongs.


The Ready to Install the Program screen appears.



- 7 Click Next. The progress screen appears.



- 8 When the installation finishes, information about the process appears. Upon successful completion, the screen shows the link that the Tomcat server uses to connect to MOVEit Central Web Admin.




- 9 Optionally select Show the Windows Installer log. Click Finish.


Repair or Remove Web Admin

You can use the install program to repair/reinstall or remove MOVEit Central Web Admin. The installation program determines whether you are doing maintenance or upgrading.


- 1 Run the installer. The Update Welcome screen appears.



- 2 Click Next. The Program Maintenance screen appears.




- 3 To fix missing or corrupt files, shortcuts or registry entries, select **Repair** and click **Next**. This process reinstalls the software. The Ready to Repair the Program screen appears.



- a) Click **Install**.


- b) When the process completes, a screen appears with information about the process.



- c) Click Finish to close the install program.


– or –

- 4 To uninstall MOVEit Central Web Admin, select **Remove**, and click **Next**. The *Remove the Program* screen appears.



- a) Review your selection. Click **Remove** to continue.
If you do not want to uninstall at this time, click **Cancel** to leave you system unchanged.

- b) When the process completes, a screen appears with information about the process.



- c) Click **Finish** to close the install program.


Connect to MOVEit Central with Web Admin

To connect to MOVEit Central, you must have both of the following:

- The location to access the MOVEit Central Web Admin
- Your MOVEit Central administrator ID and password.


- 1 From a **supported browser**, (on page 5) type the location where MOVEit Central Web Admin is installed. For example:

http://URL or system name:8080/webadmin/login



- 2 At the login page, type your administrative user and password, and click **Log In**:

3 The MOVEit Central Web Admin opens.



Index

C

Certificate Dialog • 21

Connect to MOVEit Central with Web Admin • 52

Credentials • 15

D

Database Considerations • 6

Database Type • 16

E

Email Options • 14, 22

F

Finish • 23

Folders • 18, 19

I

Install MOVEit Central • 4, 10, 38

Install MOVEit Central Web Admin • 3, 4, 38

Install or Update Web Admin • 40

L

License • 13, 26, 27

License Agreement • 12

M

Modify MOVEit Central • 4, 7, 33

O

Overview • 3

R

Ready to Update • 28, 29

Repair MOVEit Central • 4, 31

Repair or Remove Web Admin • 47

Requirements • 3, 5, 10, 52

S

Setup Options • 14, 16

Supported Features in Web Admin • 3, 39

T

Tamper Detection Key • 20

The MOVEit Central Installation Program • 4

U

Uninstall MOVEit Central • 4, 36

Update Complete • 29, 30

Update MOVEit Central • 4, 10, 26

Update Notes • 7

W

Welcome • 11, 26